Dr. DeeBee® ODBC Driver Kit (Gold Edition)

Overview

The Dr. DeeBee ODBC Driver Kit (Gold Edition) contains the complete C/C++ source code for a fully functional ODBC 3.0 driver (Level 2 API, minimum+ SQL grammar). Programmers can modify this source code to provide ODBC access their own proprietary databases.

The source code provides a complete ODBC driver implementation. The driver has the following limitations:

- Only minimum level SQL is supported, with some additional core level SQL functionality. See Appendix A for the SQL grammar supported.
- Some level 2 ODBC API calls that are not commonly used are not supported. In particular, SQLBrowseConnect, SQLTablePrivileges, SQLColumnPrivileges, SQLProcedures, and SQLProcedureColumns are not supported.
- Column and table names are not case-sensitive (this can easily be changed). String data comparisons are case sensitive.
- Interval types are not supported.
- Qualifiers or owners are not allowed on databases, tables, etc.
- There is limited query optimization.

In the source code provided, simple dBASE files (dBASE files without indexes or memos) are used as the underlying database. All dBASE specific code is isolated to two modules: ISAM.C and DBASE.C.

Our initial testing shows that this driver will work with off-the-shelf applications such as Access, Visual Basic, PowerBuilder, MFC, Visual C/C++, etc. If you encounter problems, please let us know.

New Features in the Gold Edition

This release adds the following new features to the Silver Edition:

- ODBC 3.0 compliance.
- Scrollable cursors.
- The code can be compiled on UNIX (GNU compiler, Sun OS 4.1.1)
- BETWEEN operator.
- SELECT TABLE.*.
- SELECT COUNT(FIELD).

See Appendix B for notes on how to migrate from the Silver Edition to the Gold Edition.

What You Need

In addition to the Dr. DeeBee ODBC Driver Kit (Gold Edition), you will need the following to build and distribute your ODBC driver:

- A C/C++ compiler such as Microsoft Visual C++.
- The ODBC SDK. The ODBC SDK is available directly from Microsoft as part of MSDN Level 2. Call Microsoft at 1-800-759-5474 or 1-206-882-8080 for more information. At the time of this writing, the ODBC SDK was also posted on the Microsoft web site at http://www.microsoft.com/data/odbc/download/.

It is assumed that the user has working knowledge of what ODBC is, the ODBC API, how to use ODBC, etc. Recommended reading in these areas is:

- Windows Multi-DBMS Programming; Ken North; John Wiley & Sons; 1995
- Inside ODBC; Kyle Geiger; MS Press; expected June 1995
- *The ODBC Solution*; Robert Signore, John Creamer, Micheal O. Stegman; McGraw-Hill; 1995
- Microsoft ODBC 2.0 Programmer's Reference and SDK Guide; Microsoft Press; 1994

SYWARE Support

Included with your purchase is one hour of telephone support at 617-497-1300. Additional telephone support is available on a fee-per-event basis. Questions can also be E-mailed to support@syware.com.

If you find bugs or have other feedback, we welcome your comments. Please E-mail them to support@syware.com.

Installing the Dr. DeeBee ODBC Driver Kit (Gold Edition)

WARNING:

If you are installing over a previous version of the kit, backup any old installation of the kit before installing. The installation overwrites everything in any previous installation without making any backup files.

To install the Dr. DeeBee ODBC Driver Kit (Gold Edition), do the following:

- Install your C compiler.
- Install the ODBC SDK.
- Put the installation disk in drive A: and run SETUP.EXE.

Once installed, you will see the following:

C:\DRDBDR - Your installation directory (the default)
C:\DRDBDR\SOURCE - ODBC driver source code (for Windows)
C:\DRDBDR\SOURCE\INSTALL - Source code for 32-bit Windows installer

components

C:\DRDBDR\UNIX - ODBC driver source code (for UNIX)
C:\DRDBDR\SETUP - 16-bit ODBC driver DLL and installer
C:\DRDBDR\SETUP32 - 32-bit ODBC driver DLL and installer

C:\DRDBDR\SETUP\DRDBDR.DLL is a 16-bit compiled version of the source code found in C:\DRDBDR\SOURCE. C:\DRDBDR\SETUP32\DRDBDR32.DLL is a 32-bit compiled version of the source code found in C:\DRDBDR\SOURCE.

Getting Started

You will probably want to start by rewriting ISAM.C to read and write data from your database (rather than dBASE files). Once this is done, you will have an ODBC driver for your DBMS or file format with the same limitations specified in the Overview section above. See Appendix C for a suggested strategy on how to implement ISAM.C.

After this is done, you can add functionality to your driver by modifying the rest of the code.

Distributing Your Driver

Except for DRDBDR.DLL and the files in the SETUP32 directory; none of the components in the Dr. DeeBee ODBC Driver Kit (Gold Edition) are redistributable. The driver you create using the kit (in the form of a DLL) is redistributable royalty-free in most cases. See your license (Appendix D) for more details.

If you copy C\DRDBDR\SETUP*.* to a diskette, you will have a setup disk that will load the 16-bit Dr. DeeBee ODBC Sample Driver. If you copy C\DRDBDR\SETUP32*.* to a diskette, you will have a setup disk that will load the 32-bit Dr. DeeBee ODBC Sample Driver. However, your license agreements with SYWARE only allows you to redistribute

DRDBDR.DLL and C\DRDBDR\SETUP32*.*. Your right to redistribute the other components in C\DRDBDR\SETUP can be obtained from your ODBC SDK license.

To create a setup disk for your 16-bit driver, do the following:

- Delete C:\DRDBDR\SETUP\DRDBDR.DLL.
- Copy your DLL into C\DRDBDR\SETUP.
- Edit C:\DRDBDR\SETUP\ODBC.INF as follows:
 - In the section [Dr. DeeBee Sample Driver 16], change DRDBDR.DLL to the name of your DLL, change 1998-06-12 to the date on your DLL, and change 262352 to the size of your DLL.
 - Search for "Dr. DeeBee" elsewhere in the ODBC.INF and make the appropriate changes.

To create a setup disk for your 32-bit driver, do the following:

- Delete C:\DRDBDR\SETUP32\DRDBDR32.DLL.
- Copy your DLL into C\DRDBDR\SETUP32.
- Edit C:\DRDBDR\SETUP32\ODBCLOAD.INI as appropriate.

Using C++

The kit, as installed, assumes C (not C++) compiles. If your underlying database API happens to be C++, you might want to compile the driver kit as C++. The code was written such that it will compile either way. All you have to do is change the module names from *.C to *.CPP. Two batch files (C_TO_CPP.BAT and CPP_TO_C.BAT) are provided for this purpose.

ODBC 2.x versus ODBC 3.0

If you are building a 16-bit driver, it must be ODBC 2.x compliant (ODBC 3.0 is not supported on 16-bit platforms). If you are building a 32-bit driver, the Dr. DeeBee ODBC Driver Kit (Gold Edition) will build a single driver (a single DLL) that can be used with either ODBC 2.x or ODBC 3.0.

For 16-bit drivers, the supplied makefiles will create an ODBC 2.x driver.

For 32-bit drivers, the supplied makefiles will create a hybrid ODBC 3.0/ODBC 2.x driver. Whether your driver behaves like ODBC 2.x or ODBC 3.0 depends on which ODBC Driver Manager (ODBC32.DLL) is calling it. If ODBC32.DLL is 3.0 or later, the behave like a ODBC 3.0 driver. Otherwise it will behave like an ODBC 2.x driver.

UNIX ODBC Drivers

The code in C\DRDBDR\UNIX can be compiled on UNIX systems (GNU compiler, Sun OS 4.1.1). Once you have your driver, you need to do one of two things: make it visible to one of the proprietary UNIX ODBC Driver Managers available from third parties or link the code in directly with the application that is to use the driver. Since third part ODBC Driver Manager's are proprietarty, instructions on how to make your driver visible to the Driver Manager can only be obtained from the provider of the Driver Manager.

ODBC Data Types

The Dr. DeeBee ODBC Driver Kit (Gold Edition) can support any of the ODBC data types (SQL_CHAR, SQL_INTEGER, etc.) except the interval types. The data types your driver will support depends on your underlying database. As installed, the Dr. DeeBee ODBC Driver Kit (Gold Edition) supports the dBase data types (SQL_BIT, SQL_CHAR, SQL_DATE, and SQL_DECIMAL).

There is a table of types in SQLTYPE.C, one entry for each ODBC datatype. Specify which types your driver supports by modifying this table. If your underlying database does not support one of the ODBC datatypes in this table, **do not remove the entry from this table**. Instead, just set the value of the 'supported' element in the structure to FALSE.

If your database has two datatypes that you want to map onto the same ODBC type (this happens sometimes, you'll know when it does), add extra entries to the table. Just make sure that the "more general" entry for any given ODBC data type comes first.

See the comments in SQLTYPE.C for more details.

Sorting

Sorting is used to implement the ORDER BY and GROUP BY clauses of a SELECT statement. The Dr. DeeBee ODBC Driver Kit (Gold Edition) sorts in two ways: pushdown sorts and upper-level sorts.

The pushdown sort is implemented by pushing the sorting functionality down to the ISAM layer. If the upper layers of the system determine that a pushdown sort can be used, it calls ISAMSort(). If the ISAM layer can implement the sort, the ISAM layer returns a status of NO_ISAM_ERR and a pushdown sort is done.

If the upper layers of the system determine that a pushdown sort cannot be used, or if an ISAMSort() call of a pushdown sort returns a status other then NO_ISAM_ERR, an upper-level sort is done.

Use of Indexes

To solve a query, the upper levels of the system opens a table and retrieves the records in the table. For each record retrieved, it tests the selection criteria specified and filters out the records that do not meet the criteria. This filtering can be pushed down to the ISAM layer. When this is done, the query would take less time to execute since fewer records would have to be processed by the upper levels.

This section describes this pushdown mechanism in general terms. For details, see the documentation of ISAM.H (in particular, ISAMOpenTable(), ISAMRestrict(), ISAMNextRecord(), and the declaration of COLUMNDEF).

When the upper levels of the system calls the ISAM layer to open a table, the ISAM layer returns the name and type of each of the columns. In addition to this information, the ISAM layer also returns the selectivity of each column. The selectivity is an indication of how selective the column is (for example, RECORD_ID would be very selective, NAME would be moderately selective, ZIPCODE would not be very selective).

When the upper levels of the system receives a query, it walks the predicate to find the selective clauses (based on the selectivity specified when the table was opened). After the upper levels of the system open the table, but before any records are retrieved from the table, it passes these clauses down to the ISAM layer to tell the ISAM layer "you only need to return records that satisfy this criteria". It then starts to retrieve the records from the ISAM layer. A typical ISAM implementation will use its indexes to decide which records should returned.

For example, suppose the query is:

SELECT * FROM ORDERS, ITEMS WHERE ORDER.ID = ITEM.ORDERID

the tables are:

ORDERS		ITEMS	
NAME	ID	ORDERID	ITEM
FRED	77	77	MILK
BILL	99	77	CHEESE
		99	EGGS

Also assume that the selectivity of ITEMS.ORDERID (as return by ISAMOpenTable()) is non-zero.

In this case, the system would generate the following sequence of ISAM calls:

```
ISAMOpenTable(ORDERS)
ISAMOpenTable(ITEMS)
ISAMRewind(ORDERS)
 ISAMNextRecord(ORDERS) (which positions to FRED's record)
   ISAMRestrict(ITEMS, ORDERID == 77)
   ISAMRewind(ITEMS)
     ISAMNextRecord(ITEMS) (which positions to the MILK record)
    ISAMNextRecord(ITEMS) (which positions to the CHEESE record)
     ISAMNextRecord(ITEMS) (which returns end-of-file)
 ISAMNextRecord(ORDERS) (which positions to BILL's record)
   ISAMRestrict(ITEMS, ORDERID == 99)
   ISAMRewind(ITEMS)
     ISAMNextRecord(ITEMS) (which positions to the EGGS record)
     ISAMNextRecord(ITEMS) (which returns end-of-file)
 ISAMNextRecord(ORDERS) (which returns end-of-file)
ISAMCloseTable(ORDERS)
ISAMCloseTable(ITEMS)
```

Transactions

Transactions are supported to the extent they are supported by the underlying database. For example, if you were building a driver for a true relational engine (such as Oracle or SQL Server), the transaction mechanism implemented by the engine could be used to implement transactions in the driver. On the other hand, if you were building a driver for simple text files, transactions would not be supported since regular file input/output does not support transaction operations such as commit or rollback.

Exposing the underlying database's transaction capabilities is relatively straight forward. Initially, you specify the transaction capabilities of your underlying system. There are a variety of options ranging from "transactions are not supported" to "full transaction support". If you specify that transactions are supported, they are initiated implicitly by calls to ISAM layer. The ISAM layer receives explicit calls to commit or rollback a transaction.

Transactions are described in detail in ISAM.H.

Passthrough SQL

Before an SQL query is processed by the upper levels of the system, it is first passed to ISAMPrepare(). This gives the ISAM layer the option of passing it to a SQL backend or having the upper levels of the system process it.

ISAMPrepare() responds in one of three ways:

- 1. It indicates that the upper levels of the system should process the query.
- 2. It indicates that the query will be processed by the backend and no result set will be returned (for example, an INSERT statement).
- 3. It indicates that the query will be processed by the backend and a result set will be returned (for example, a SELECT statement).

If a result set is returned, it is returned like any other table. The ISAMPrepare() call returns the name of this virtual table. The upper level of the system will process a "SELECT * FROM <virtual-table>" to retrieve the values.

After ISAMPrepare() is called, ISAMExecute() is called to actually run the query. ISAMExecute() may be called several times after a single call to ISAMPrepare(). When the upper levels of the system no longer needs the query, ISAMFreeStatement() is called.

The SQL prepared by ISAMPrepare() can contain parameters, and these parameters are specified by ISAMParameter() calls that are made after the call to ISAMPrepare() but before the ISAMExecute().

The sample code shows two simple examples of passthrough SQL. The first processes the query "SQL" by returning a table with one column and two rows. The second processes the query "MessageBox(?,?)" by putting up a message box whose content and title are specified by parameters one and two (respectively).

Architecture

The architecture of the source codes is shown in the following diagram:




Figure 1: Source Code Architecture

The modules are:

CATALOG.C - ODBC entry points for catalog functions:

SQLTables

SQLColumns

SQLStatistics

SQLTablePrivileges

SQLColumnPrivileges

SQLSpecialColumns

SQLPrimaryKeys

SQLForeignKeys

SQLProcedures

SQLProcedureColumns

CONNECT.C - ODBC entry points for database connection functions:

SQLAllocEnv

SQLAllocConnect

SQLConnect

SQLDriverConnect

SQLBrowseConnect

```
SQLDisconnect
```

SQLFreeConnect

SQLFreeEnv

EXECUTE.C - ODBC entry points for SQL execution functions:

SOLExecute

SQLExecDirect

SQLNativeSql

SQLParamData

SQLPutData

SQLCancel

INFO.C - ODBC entry points for informational functions:

SQLGetInfo

SQLGetTypeInfo

SQLGetFunctions

OPTIONS.C - ODBC entry points for connection and statement option functions:

SQLSetConnectOption

SQLSetStmtOption

SQLGetConnectOption

SQLGetStmtOption

PREPARE.C - ODBC entry points for query preparation setup functions:

SQLAllocStmt

SQLFreeStmt

SQLPrepare

SQLBindParameter

SQLDescribeParam

SQLParamOptions

SQLNumParams

SQLSetScrollOptions

SQLSetCursorName

SQLGetCursorName

RESULTS.C - ODBC entry points for result retrieval functions:

SQLNumResultCols

SQLDescribeCol

SQLColAttributes

SQLBindCol

SQLFetch

SQLGetData

SQLMoreResults

SQLRowCount

SQLSetPos

SQLExtendedFetch

SQLError

TRANSACT.C - ODBC entry points for transaction functions:

SQLTransact

ODBC30.C - ODBC entry points for ODBC30 functions:

SQLAllocHandle

SQLBulkOperations

SQLCloseCursor

SQLColAttribute

SQLCopyDesc

SQLEndTran

SQLFetchScroll

SQLFreeHandle

SQLGetConnectAttr

SQLGetDescField

SQLGetDescRec

SQLGetDiagField

SQLGetDiagRec

SQLGetEnvAttr

SQLGetStmtAttr

SQLSetConnectAttr

SQLSetDescField

SQLSetDescRec

SQLSetEnvAttr

SQLSetStmtAttr

SORT.C - Sorting operations.

DLL.C - LibMain, etc.

PARSE.C - Parses SQL statement (as a text string) and creates a parse tree. This module implements a recursive descent parser for SQL.

SEMANTIC.C - Check a parse tree for semantic correctness. This module also contains a routine to display parse trees on the debug monitor.

OPTIMIZE.C - Query optimizer. Currently the only optimization done is to find restrictions on tables to cut down the search space.

EVALUATE.C - Evaluates SQL expressions and executes SQL statements.

COLDEFS.C - This module contains the definition of the columns returned by the virtual tables returned by the catalog functions and SQLGetTypeInfo(). It is unlikely you will ever need to modify these.

SQLTYPE.C - Definition of the SQL types supported by the driver. As installed, the Dr. DeeBee ODBC Driver Kit (Gold Edition) supports SQL_BIT, SQL_CHAR, SQL_DATE, and SQL_DECIMAL. If you want your driver to support other types, modify the entries in the tables in this module. See the comments in SQLTYPE.C.

BCD.C- Operations to compare, negate, add, subtract, multiply, and divide Binary Coded Decimal values.

SCALAR.C- Implementation of scalar functions.

ISAM.C - Low level record access interface. The majority of the work needed to access data in a format other than dBASE is done in this module. The driver writer is expected to provide the implementation of the following routines (as documented in ISAM.H):

ISAMOpen

ISAMGetTableList

ISAMGetNextTableName

ISAMFreeTableList

ISAMForeignKeys

ISAMCreateTable

ISAMAddColumn

ISAMCreateIndex

ISAMDeleteIndex

ISAMOpenTable

ISAMRewind

ISAMSort

ISAMRestrict

ISAMNextRecord

ISAMGetData

ISAMPutData

ISAMInsertRecord

ISAMUpdateRecord

ISAMDeleteRecord

ISAMGetBookmark

ISAMPosition

ISAMCloseTable

ISAMDeleteTable

ISAMPrepare

ISAMParameter

ISAMExecute

ISAMFreeStatement

ISAMClose

ISAMSetTxnInfo

ISAMCommitTxn

ISAMRollbackTxn

ISAMGetErrorMessage

ISAMGetColumnType

ISAMCaseSensitive

ISAMName

ISAMVersion

ISAMDriver

ISAMMax Table Name Length

ISAMMaxColumnNameLength

ISAMUser

ISAMDatabase

UTIL.C - Utility functions:

CharToDouble - Converts strings to doubles

CharToDate - Converts strings to dates

CharToTime - Converts strings to times

CharToTimestamp - Converts strings to timestamps

DoubleToChar - Converts doubles to strings

DateToChar - Converts dates to strings

TimeToChar - Converts times to strings

TimestampToChar - Converts timestamps to strings

ReturnString - Copies strings and their length

ReturnStringD - Copies strings and their length

ConvertSqlToC - Converts data from one type to another

PatternMatch - Wildcard pattern matching

TrueSize - Determines size of a string

DBASE.C - Routines to read and write records in dBASE files. This module is only used by ISAM.C.

TRACE.C - Tracing facilities. To enable tracing, set ISAM_TRACE to TRUE in UTIL.H (not TRACE.H), delete all your .OBJ and .PCH files, and recompile. Setting ISAM_TRACE to TRUE will trace every ISAM.C call. The output is sent to the debug window (DBWIN.EXE).

Tips and Tricks

The following tips and tricks will make your development easier:

- 1. Before modifying ISAM.C or any other modules, create a project (see Appendix C for a list of files your project should include) and recompile the system. This will allow you find problems in your development environment independently of bugs you might enter into the code.
- 2. Run SETUP.EXE in C\DRDBDR\SETUP or C\DRDBDR\SETUP32 to install the driver and create a datasource (MYSOURCE) using the driver. When creating the new datasource, be sure to use the "Database" edit control to specify the name of the directory that holds the .DBF files.

Once you do this, redirect the MYSOURCE datasource to use the DLL created by your compiler rather than the one in the Windows system directory. To do this...

- ...in Windows 3.x Using a text editor, such as NOTEPAD, edit
 C:\WINDOWS\ODBC.INI. Look for the [MYSOURCE] section and change
 the <file> designated by the "Driver=<file>" keyword/value pair to specify the
 complete pathname of the .DLL file created by your compilation.
- ...in Windows NT/Win95 Using the registry editor change the value of /HKEY_CURRENT_USER/Software/ODBC/ODBC.INI/MYSOURCE/Driver to specify the complete pathname of the .DLL file created by your compilation.

Once you do this, you will not have to reinstall after each compilation of your driver, since the MYSOURCE datasource will always be pointing at the DLL just created.

- 3. If you are using Microsoft Visual C++ to create a 16-bit driver, set "Calling Program" under Options | Debug to be C:\ODBCSDK\BIN\ODBCTEST.EXE. You can then set breakpoints in your driver, and run (DEBUG | GO).
- 4. If you are using Microsoft Visual C++ to create a 32-bit driver, set the executable to use when running under the debugger to C\ODBCSDK\BIN32\ODBCTE32.EXE. You can then set breakpoints in your driver, and run (DEBUG | GO).
- 5. You can easily generate a trace of the calls to ISAM.C by setting the ISAM_TRACE flag to TRUE and recompiling. This flag is declared in UTIL.H.

Appendix A: SQL Grammar supported

```
(Grammar that is new in the Gold Edition is in boldface)
statement ::= CREATE create | DROP drop | SELECT select orderby | INSERT insert |
               DELETE delete | UPDATE update | passthroughSQL
passthroughSQL ::= any statement supported by the backend
create ::= TABLE tablename ( createcols )
               INDEX indexname ON tablename (indexcolumns)
indexcolumns ::= indexcolumn | indexcolumn , indexcolumns
indexcolumn ::= columnname asc
createcols ::= createcol, createcols | createcol
createcol ::= columnname datatype | columnname datatype ( integer ) |
               columnname datatype (integer, integer)
drop ::= TABLE tablename | INDEX indexname
select ::= selectcols FROM tablelist where groupby having
delete ::= FROM tablename where
insert ::= INTO tablename insertvals
update ::= tablename SET setlist where
setlist ::= set | setlist , set
set ::= columnname = NULL | columnname = expression
insertvals ::= ( columnlist ) VALUES ( valuelist ) | VALUES ( valuelist ) |
               (columnlist) VALUES (SELECT select)
               VALUES ( SELECT select )
columnlist ::= columnname , columnlist | columnname
valuelist ::= NULL, valuelist | expression, valuelist | expression | NULL
```

```
selectcols ::= selectallcols * | selectallcols selectlist
selectallcols ::= | ALL | DISTINCT
selectlist ::= selectlistitem, selectlist | selectlistitem
selectlistitem ::= expression | expression aliasname | expression AS aliasname |
               aliasname, *
where ::= | WHERE boolean
having ::= | HAVING boolean
boolean ::= and | and OR boolean
and ::= not | not AND and
not ::= comparison | NOT comparison
comparison ::= ( boolean ) | colref IS NULL | colref IS NOT NULL |
               expression LIKE pattern | expression NOT LIKE pattern |
               expression IN (valuelist) | expression NOT IN (valuelist) |
               expression op expression | EXISTS ( SELECT select ) |
               expression op selectop ( SELECT select ) |
               expression IN ( SELECT select ) |
               expression NOT IN ( SELECT select ) |
               expression BETWEEN expression AND expression
               expression NOT BETWEEN expression AND expression
selectop ::= | ALL | ANY
op ::= > | >= | < | <= | = | <>
pattern ::= string | ? | USER
expression ::= expression + times | expression - times | times
times ::= times * neg | times / neg | neg
neg ::= term | + term | - term
term ::= ( expression ) | colref | simpleterm | aggterm | scalar
```

```
scalar ::= scalarescape | scalarshorthand
scalarescape ::= --*(VENDOR(MICROSOFT),PRODUCT(ODBC) FN fn )*--
scalarshorthand ::= { FN fn }
fn ::= functionname ( valuelist ) | functionname ( ) |
              POSITION (expression IN expression)
              EXTRACT (expression FROM expression)
aggterm ::= COUNT (*) | AVG (expression) | MAX (expression) |
              MIN (expression) | SUM (expression) | COUNT (expression)
simpleterm ::= string | realnumber | ? | USER | date | time | timestamp
groupby ::= | GROUP BY groupbyterms
groupbyterms ::= colref | colref , groupbyterms
orderby ::= | ORDER BY orderbyterms
orderbyterms ::= orderbyterm | orderbyterm , orderbyterms
orderbyterm ::= colref asc | integer asc
asc ::= |ASC|DESC
colref ::= aliasname . columnname | columnname
tablelist ::= tablelistitem, tablelist | tablelistitem
tablelistitem ::= tableref | outerjoin
outerjoin ::= ojescape | ojshorthand
ojescape ::= --*(VENDOR(MICROSOFT),PRODUCT(ODBC) OJ oj )*--
ojshorthand ::= { OJ oj }
oj := tableref LEFT OUTER JOIN tableref ON boolean |
              tableref LEFT OUTER JOIN of ON boolean
tableref ::= tablename | tablename aliasname
```

```
indexname ::= identifier
functionname ::= identifier
tablename ::= identifier
datatype ::= identifier
columnname ::= identifier
aliasname ::= identifier
identifier ::= an identifier (identifiers containing spaces must be enclosed in double quotes)
string ::= a string (enclosed in single quotes)
realnumber ::= a non-negative real number (including E notation)
integer ::= a non-negative integer
date ::= dateescape | dateshorthand
dateescape ::= --*(VENDOR(MICROSOFT),PRODUCT(ODBC) d dateval )*--
dateshorthand ::= { d dateval }
dateval ::= a date in yyyy-mm-dd format in single quotes (for example, '1996-02-05')
time ::= timeescape | timeshorthand
timeescape ::= --*(VENDOR(MICROSOFT), PRODUCT(ODBC) t timeval )*--
timeshorthand ::= { t timeval }
timeval ::= a time in hh:mm:ss format in single quotes (for example, '10:19:48')
timestamp ::= timestampescape | timestampshorthand
timestampescape ::= --*(VENDOR(MICROSOFT),PRODUCT(ODBC) ts timestampval )*--
timestampshorthand ::= { ts timestampval }
```

timestampval ::= a timestamp in yyyy-mm-dd hh:mm:ss[.ffffff] format in single quotes (for example, '1996-02-05 10:19:48.529')				

Appendix B: Migrating from the Silver Edition to the Gold Edition

If you implemented your old driver by only modifying ISAM.C and DBASE.C, for the most part, the ISAM.C and DBASE.C you implemented for the Silver Edition can be used with only minor chages in the Gold Edition. If you modified any other code you will have to re-implement those changes.

In ISAM.C there are four changes you must make:

1. szDefault has been added to ISAMCOLUMNDEF.

This field specifies the default value used when inserting records into the table.

Note: To preserve the semantics of the Silver edition, set this value to "NULL" (without the quotes).

2. The first argument of the PatternMatch() routine in UTIL.H has been chnaged from a boolean to a character.

If it is '\0' there is no escape character for pattern matching. Otherwise, it is the escape character to use when pattern matching. For backward compatibility, if this character is TRUE, '\\' is used.

Note: To preserve the semantics of the Silver edition, set this value to '' (if it was TRUE) or ''0' (if it was FALSE).

3. ISAMForeignKey has an added argument: lpfDeferrability.

Set this to the applicable deferrability (see the documentation in ISAM.H).

Note: To preserve the semantics of the SIIver edition, set this value to a -1.

4. ISAMExecute has an added parameter: lpfFunctionCode.

Set this to indicate the type of SQL statement just executed (use one of the SQL_DIAG_* codes in SQL.H).

Note: To preserve the semantics of the Silver edition, set this value to SQL_DIAG_UNKNOWN_STATEMENT.

Dr. DeeBee OD	BC Driver Kit (Go	old Edition)

Appendix C: Implementation Strategy for ISAM.C

The first thing you want to do is create a project to build your driver with. If you happen to be building a 16-bit driver using Microsoft Visual C/C++ 1.5, you can use the DRDBDR.MAK file provided. If you happen to be building a 32-bit driver using Microsoft Visual C/C++ 2.0, 3.0, 4.0, or 5.0 you can use the DRDBDR32.MAK file provided. Otherwise you will have to build your own project containing the following files (a sample makefile for UNIX builds is provided):

BCD.C	SCALAR.C	SCALAR.H
CATALOG.C	SEMANTIC.C	SEMANTIC.H
COLDEFS.C	SETUP.C	SQLTYPE.H
CONNECT.C	SORT.C	TRACE.H
DBASE.C	SQLTYPE.C	UNIXDEFS.H
DLL.C	TRACE.C	UNIXINCL.H
DRDBDR.C	TRANSACT.C	UNIXSQL.H
EVALUATE.C	UTIL.C	UTIL.H
EXECUTE.C		
INFO.C	BCD.H	DRDBDR.RC
ISAM.C	DBASE.H	DRDB.ICO
ODBC30.C	DRDBDR.H	
OPTIMIZE.C	EVALUATE.H	ODBCINST.LIB (if 16-bit)
OPTIONS.C	ISAM.H	ODBCCP32.LIB (if 32-bit)
PARSE.C	ODBC30.H	
PREPARE.C	OPTIMIZE.H	DRDBDR.DEF (if 16-bit)
RESULTS.C	PARSE.H	DRDBDR32.DEF (if 32-bit)

Once your project is set up, it is suggested that you use the following code...test...code...test...code...test strategy when rewriting ISAM.C to connect to your database. On windows based systems, the testing can be done using ODBC Test (from the ODBC SDK). On UNIX systems, the testing canbe done by compiling and running the code in ISAMTEXT.C. The testing assumes that there is a table called EMP with a column called NAME and a column called SALARY:

Step 1: Connecting:

Code: ISAMOpen()

ISAMClose()

ISAMGetErrorMessage()

Test: Connect | Full Connect

Connect | Full Disconnect

Note: For now, disable transactions by setting fTxnCapable in LPISAM to SQL TC NONE.

Step 2: Get driver description:

Code: ISAMCaseSensitive()

ISAMMaxColumnNameLength()
ISAMMaxTableNameLength()

ISAMName()
ISAMVersion()
ISAMDriver()
ISAMUser()
ISAMDatabase()

Test: Connect | Full Connect

Connect | SQLGetInfo(SQL_IDENTIFIER_CASE)

Connect | SQLGetInfo(SQL_MAX_COLUMN_NAME_LEN)
Connect | SQLGetInfo(SQL_MAX_TABLE_NAME_LEN)

Connect | SQLGetInfo(SQL_DBMS_NAME) Connect | SQLGetInfo(SQL_DBMS_VER) Connect | SQLGetInfo(SQL_DRIVER_NAME) Connect | SQLGetInfo(SQL_USER_NAME)

Connect | SQLGetInfo(SQL_DATABASE_NAME)

Connect | Full Disconnect

Step 3: List of tables:

Code: ISAMGetTableList()

ISAMGetNextTableName()
ISAMFreeTableList()

Test: Connect | Full Connect

Catalog | SQLTables Results | GetDataAll Connect | Full Disconnect

Step 4: List of columns for a table:

Code: ISAMOpenTable()

ISAMCloseTable()

Test: Connect | Full Connect

Catalog | SQLColumns(EMP)

Results | GetDataAll

Connect | Full Disconnect

Step 5: Simple select:

Code: ISAMRewind()
ISAMNextRecord()
ISAMGetData()

Test: Connect | Full Connect

Statement | SQLExecDirect("select * from EMP")

Results | GetDataAll Connect | Full Disconnect

Step 6: Select with restriction:

Code: ISAMRestrict()

Test: Connect | Full Connect

Statement | SQLExecDirect("select * from EMP where NAME = 'FRED'")

Results | GetDataAll Connect | Full Disconnect

Note: ISAMRestrict() will only be called if ISAMTableOpen() returns a non-zero value for fSelectivity for the NAME column.

Step 7: Select with ORDER BY clause using an upper-level sort:

Code: ISAMGetBookmark()
ISAMPosition()

Test: Connect | Full Connect

Statement | SQLExecDirect("select * from EMP order by NAME")

Results | GetDataAll Connect | Full Disconnect

Note: Supress pushdown sorts by implementing ISAMSort() as:

```
if (count != 0)
    return ISAM_NOTSUPPORTED;
else
    return NO ISAM ERR;
```

Step 8: Select with ORDER BY clause using a pushdown sort:

Code: ISAMSort()

Test: Connect | Full Connect

Statement | SQLExecDirect("select * from EMP order by NAME")

Results | GetDataAll Connect | Full Disconnect

Step 9: Modifying data:

Code: ISAMPutData()

ISAMUpdateRecord()

Test: Connect | Full Connect

Statement | SQLExecDirect("update EMP set SALARY = 20000")

Connect | Full Disconnect

Step 10: Inserting records:

Code: ISAMInsertRecord()

Test: Connect | Full Connect

Statement | SQLExecDirect(

"insert into EMP(NAME, SALARY) values ('CRAIG', 20000)")

Connect | Full Disconnect

Step 11: Deleting records:

Code: ISAMDeleteRecord()

Test: Connect | Full Connect

Statement | SQLExecDirect("delete from EMP where NAME ='CRAIG"")

Connect | Full Disconnect

Step 12: Creating a table:

Code: ISAMCreateTable()

ISAMAddColumn()

Test: Connect | Full Connect

Statement | SQLExecDirect(

"create table EMP2(NAME CHAR(10), SALARY DECIMAL(14,2))")

Connect | Full Disconnect

Step 13: Deleting a table:

Code: ISAMDeleteTable()

Test: Connect | Full Connect

Statement | SQLExecDirect("drop table EMP2")

Connect | Full Disconnect

Step 14: Passthrough SQL:

Code: ISAMPrepare()

ISAMParameter()
ISAMExecute()

ISAMFreeStatement()

Test: Connect | Full Connect

Statement | SQLExecDirect(<<SQL to be passed to the back end >>)

If the query returns a result set: Results | GetDataAll

Connect | Full Disconnect

Step 15: Creating an index:

Code: ISAMCreateIndex()

Test: Connect | Full Connect

Statement | SQLExecDirect("create index EMPINDEX on EMP(NAME)")

Connect | Full Disconnect

Step 16: Deleting an index:

Code: ISAMDeleteIndex()

Test: Connect | Full Connect

Statement | SQLExecDirect("drop index EMPINDEX")

Connect | Full Disconnect

Step 17: Foreign Keys:

Code: ISAMForeignKey()

Test: Connect | Full Connect

Catalog | SQLForeignKeys(EMP)

Results | GetDataAll Connect | Full Disconnect

Step 18: Transactions:

Code: ISAMSetTxnIsolation()

ISAMCommitTxn()
ISAMRollbackTxn()

Test: Connect | Full Connect

Statement | SQLExecDirect(

"insert into EMP(NAME, SALARY) values ('CRAIG', 20000)")

If you are using the ODBC 3 SDK:

Environment | SQLEndTran(SQL_ROLLBACK)

If you are using the ODBC 2 SDK:

Misc | SQLTransact(SQL_ROLLBACK)

Connect | Full Disconnect

Note: Don't forget to enable transactions by setting fTxnCapable in LPISAM to something other than SQL_TC_NONE.

Appendix D: SYWARE License Agreement

Dr. DeeBee ODBC Driver Kit (Gold Edition)

SYWARE SOFTWARE LICENSE

- 1. GRANT OF LICENSE. SYWARE grants you the right to use the enclosed SYWARE software product in the manner provided below:
- a. You may use one copy of the SYWARE software product identified above, which includes "online" or electronic documents (the "SOFTWARE") on a single computer. The SOFTWARE is in "use" on a computer when it is loaded into temporary memory (i.e., RAM) or installed into permanent memory (e.g., hard disk, CD-ROM, or other storage device) of that computer. However, installation on a network server for the sole purpose of internal distribution to one or more other computer(s) shall not constitute "use" for which a separate license is required, provided you have a separate license for each computer to which the SOFTWARE is distributed.
- b. Solely with respect to the electronic documents, you may make unlimited number of copies (either in hardcopy or electronic fαm), provided that such copies shall be used only for internal purposes and are not republished or distributed beyond the user's premises.
- 2. If the SOFTWARE is an upgrade from a SYWARE product, you may now use that upgraded product only in accordance with this License.
- 3. COPYRIGHT. The SOFTWARE (including any images, "applets", photographs, animations, video, audio, music, and text incorporated in the SOFTWARE) is owned by SYWARE or its suppliers and is protected by United States copyright laws and international treaty provisions. Therefore you must treat the SOFTWARE like any other copyrighted material (e.g. a book or recording) except that you may either (a) make one copy of the SOFTWARE solely for backup or archival purposes, or (b) transfer the software to a single hard disk provided you keep the original solely for backup or archival purposes. You may not copy the printed materials accompanying the SOFTWARE
- 4. OTHER RESTRICTIONS. You may not rent or lease the SOFTWARE. You may not transfer the SOFTWARE. You may not reverse engineer, decompile, or disassemble the SOFTWARE except to the extent such foregoing restriction is expressly prohibited by applicable law.
- 5. REDISTRIBUTABLE COMPONENTS.
- a. **Sample Code.** Not withstanding Section 1, SYWARE grants you the right to use and modify the source code version of the SOFTWARE located in \DRDBDR\SOURCE and \DRDBDR\UNIX ("SAMPLE CODE") <u>provided</u> you comply with Section 5.c. You may not distribute SAMPLE CODE, or any modified version of SAMPLE CODE, in source code form.
- b. Redistributable Files. Notwithstanding Section 1, SYWARE grants you a non-exclusive right to reproduce and distribute the object code version of those portions of the SAMPLE CODE, \DRDBDR\SETUP16\DRDBDR.DLL, and \DRDBDR\SETUP32*.* (collectively called the REDISTRIBUTABLES), provided you comply with Section 5.c. and that the object code version of the SAMPLE CODE, or any modified version of the SAMPLE CODE, is an ODBC driver and is only capable of accessing a single DBMS or file format.
- c. Redistribution Requirements. If you redistribute the REDISTRIBUTABLES, you must (i) not use SYWARE's name, logo, trademarks, to market your software application product; (ii) include a valid copyright notice on your software product; (iii) agree to indemnify, hold harmless, and defend SYWARE from and against any claims or lawsuits, including attorney's fees, that arise or result from the use or distribution of your software application product; and (iv) do not permit further distribution of the REDISTRIBUTABLES by your end-user

The license in this section to distribute the REDISTRIBUTABLES is royalty-free.

6. EXPORT RESTRICTIONS. You agree that neither you nor your customers intends to or will, directly or indirectly, export or transmit (i) the SOFTWARE or related documentation and technical data or (ii) your software product as described in section 5 of this License (or any part thereof), or process, or service that is the direct product of the SOFTWARE, to any country to which such export or transmission is restricted by any applicable U.S. regulation or statute, without prior written consent, if required, of the Bureau of Export Administration of the U.S. Department of Commerce, or such other governmental entity as may have jurisdiction over such export or transmission.

LIMITED WARRANTY

LIMITED WARRANTY. Except with respect to the REDISTRIBUTABLES, which are provided "as-is", without warranty of any kind, SYWARE warrants that (a) the SOFTWARE will perform substantially in accordance with the accompanying written materials for a period of ninety (90) days from the date of receipt, and (b) any hardware accompanying the SOFTWARE will be free from defects in materials and workmanship under normal use and service for a period of one (1) year from date of receipt. Any implied warranties on the SOFTWARE and hardware are limited to ninety (90) days and one (1) year, respectively. Some states/jurisdictions do not allow limitations on duration of an implied warranty, so the above limitation may not apply to you.

CUSTOMER REMEDIES. SYWARE's and its suppliers' entire liability and your exclusive remedy shall be, at SYWARE's option, either (a) return of the price paid, or (b) repair or replacement of the SOFTWARE or hardware that does not meet SYWARE's Limited Warranty and which is returned to SYWARE with a copy of your receipt. This Limited Warranty is void if failure of the SOFTWARE or hardware has resulted from accident, abuse, or misapplication. Any replacement SOFTWARE or hardware will be warranted for the remainder of the original warranty period or thirty (30) days, whichever is longer. Outside the United States, neither these remedies nor any product support services offered by SYWARE are not available without proof of purchase from an authorized U.S. source.

NO OTHER WARRANTIES. To the maximum extent permitted by applicable law, SYWARE and its suppliers disclaim all other warranties, either express or implied, including, but not limited to, implied warranties of merchantability and fitness for a particular purpose, with regard to the SOFTWARE, the accompanying written materials, and any accompanying hardware.

This limited warranty gives you specific legal rights. You may have others, which vary from state/jurisdiction to state/jurisdiction.

NO LIABILITY FOR CONSEQUENTIAL DAMAGES. To the maximum extent permitted by applicable law, in no event shall SYWARE or its suppliers be liable for any damages whatsoever (including, without limitation, damages for loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the use of or inability to use this SYWARE product, even if SYWARE has been advised of the possibility of such damages. Because some states/jurisdictions do not allow the exclusion or limitation of liability for consequential or incidental damages, the above limitation may not apply to you.

This Agreement is governed by the laws of the Commonwealth of Massachusetts.

For Licensee:	For SYWARE:
X	Χ
Name/Title:	Seymour A. Danberg, President
Date:	Date:
Date:	Date: